

JUMP MENU

► Get Started

- Restart Your Computer (refresh your RAM)
- Follow the Setup Steps
- Workspace Overview

► Organize Your Files

- Organized Files vs. Lost Files
- Class Project (Simple)
- Pro Project (Elaborate)

► Create a New Project

- Open Premiere
- Name Your Project
- Connect to Your Master Folder
- Set “Edit” Workspace

► Import Media

- Drag and Drop Folders

► Create a Timeline Sequence

- Don’t Do This / Do This Instead
- Settings
- Drag Video Clip to Timeline
- If Your Clip is a Different Size Than Your Video Screen

► Effect Controls► Choose Your Path► Get Around

- Play Your Video on the Timeline
- How to Zoom & Move
- Timeline Track Controls

► Color Corrections► Edit Clips

- Cut / Move / Delete Clips
- Copy / Paste Clips
- Delete Space / Ripple Delete
- Shorten Clips
- (Optional) Pre-edit a Clip

► Add Audio

- Add Audio to Timeline
- Adjust Volume as Needed
- Fade Music In and Out
- Sound Adjustments
- Unlink Audio
- Change Audio Source

► Add Transitions & Effects

- Slow Motion /Fast Motion
- Transitions

► Add Text Effects

- Text Tool
- Text Effects
- Text Animation Templates
- Add Captions

► Create Animation► Replace Backgrounds

Export Your Video

► Troubleshooting

- My computer FROZE UP / Isn’t Working
- My Exported Video is Overexposed
- My Exported Video Has Image, No Sound

Get Started

[BACK TO TOP](#)

■ STEP 1: RESTART YOUR COMPUTER (refresh your RAM)

Restart your computer at the start and during any work session (several times) because your computer will slow down gradually when you use big programs like Premiere Pro. It means your RAM is running low (Random Access Memory). RAM refreshes when you restart your computer.



FOLLOW THE FIRST SETUP STEPS BELOW (even if you know Premiere Pro)

You could lose your project or a lot of time if it's not set up properly. Please follow the steps below until we get to "Choose Your Path" section, where you can choose "Advanced" to take off on your own or "Beginner" to complete your project step-by-step.

■ WORKSPACE OVERVIEW:

Below is your workspace. Change the size of any panel by clicking and dragging.

Effects Controls

Optional way to input properties numerically (such as scale, position, opacity, rotation, etc.)

Source Panel

Pre-edit clips you want to use before dragging them to the timeline, or add effects

Program Panel

Play video that's currently on your timeline.



Project Panel

(includes Media Browser)

Import your videos, photos, etc., here (drag/drop) and perform many other tasks.

Timeline Panel

Drag video clips here from the project panel. First, start a new sequence (Cntrl/Command-N)

Organize Your Files


[BACK TO TOP](#)

■ ORGANIZED FILES vs. LOST FILES

You'll risk losing your whole project easily if your files are not properly organized. So this is the most important step you will take in your project.



■ CLASS PROJECT (simple organization)




1. Create a **master folder** on your desktop.
2. Inside that folder, create individual folders for your music, videoclips, and images (name them whatever you choose).
3. **Never rename or move** these folders after they're created.
4. If you want to move or copy your project (e.g., to back it up), move **the whole master folder with all the files inside**.
5. When you want to open your project to work on it, **open the project file from inside your master folder, NOT from inside Premiere Pro**.

WHY? Because students can get confused when Premiere Pro shows them images of the most recent files it detects—these may or may not be your real files. Your files do not exist inside Premiere Pro—they are on your laptop (backed up to the cloud server you choose).

■ PRO PROJECT (example of elaborate file organization)


You don't need to do this now, but keep in mind pros use different file naming conventions for elaborate projects.



Create a New Project in Premiere


[BACK TO TOP](#)

OPEN PREMIERE. Click “New Project” button.




NAME YOUR PROJECT

1. In the new screen, ignore all images Adobe is trying to sell you (or hook you on).
2. In the top left “Project Name” area, name your video (this will be the name of your saved file).




CONNECT TO YOUR MASTER FOLDER


1. Click on “Project Location” (upper center).
2. Click “Choose Location.”




3. Browse to your MASTER FOLDER, select it, and click “Select Folder,” then “Create.”



4. You will see your full workspace open for a new project.




5. Check your master folder on your desktop. Open your master folder on your desktop to make sure it now [contains your .prproj file inside](#), along with the folders you created. If it is not inside your master folder, start over from the top of these instructions.



■ SET “EDIT” WORKSPACE

In Premiere, make sure you are in the “Edit” Workspace.

Upper Left




Import Media


[BACK TO TOP](#)

DRAG AND DROP FOLDERS

1. Open your MASTER FOLDER on your desktop to reveal the inside folders.
2. Drag and drop those inside folders (video, music, image, etc.) into the Project Panel in Premiere.



3. Click the "List View" icon at the bottom of the panel to see files easily.




NOTE: Folders with just one file will show the file and not the folder (weird, I know).

Create a New Timeline Sequence

[BACK TO TOP](#)

A sequence is the space where you build your video on a timeline. It includes your screen dimensions and other important specifications.




STOP. This isn't the point yet to take off and experiment. Follow the steps below carefully below to set up your first sequence so you don't get your project in trouble from the get-go.

DON'T DO THIS

Don't drag a video to your timeline area to start your sequence. While this works, it will cause your screen size to be created in whatever size the clip is that you dragged over. So, your whole video could be too small or too big.


DO THIS INSTEAD: CREATE A SEQUENCE

Go to [File > New > Sequence](#) OR use shortcut Command/Ctrl-N



SEQUENCE SETTINGS (your video dimensions)

In the new window, click on “Settings” and enter the info in the side bar below. Enter the screen dimensions below OR see [Sprout Social for Social media dimensions](#) you might want.



SETTINGS EXAMPLES FOR SOCIAL MEDIA:

Editing Mode:
DSLR or “Custom”

Timebase: 29.97 frames/sec
for high quality


Frame Size
[for horizontal videos]:
1920 horizontal
1080 vertical

Frame Size
[for vertical videos]:
1080 horizontal
1920 vertical

Working Color Space:
Rec. 709


Check the Box:
Auto Tone Map Media
(adjusts iPhone colors properly)

Click OK.




You will see your new sequence, including:

- a new **timeline** (this is where most of your work will be done)
- a **video screen area** (black rectangle, upper right)
- a new **file called Sequence 01** in your project panel (lower left).




DRAG A VIDEO CLIP TO THE TIMELINE

1. Now you can **drag and drop** a video from your **videoclips** folder to your **timeline** on the **v1** track.
2. You will see the **video and audio tracks appear together** in the timeline.



3. If you receive a warning that your clip does not match the sequence you created, click “[Keep existing settings](#)” to retain the dimensions of the video you’re creating (see below).




■ **IF YOUR CLIP APPEARS A DIFFERENT SIZE THAN YOUR VIDEO SCREEN**

If your clip appears to be a different size than your video screen in the program panel:

[Double-click the clip and drag it larger or smaller](#) (or use the options below).

This is also how you can create the effect of a closer shot (closeup, etc.)

NOTE: If you stretch your video too much, it could pixelate.



OPTION 1: [double-click the image of the video](#) and drag it to larger or smaller dimensions as needed.

OPTION 2: right-click on the clip on the timeline and select “[Scale to Frame Size.](#)”

OPTION 3: In the [Effects Control Panel](#) (upper left), change scale of the clip (instead of 100%, type a new number).

OPTION 4: Change your video screen to match your clip instead, if you want to (Sequence > Settings)

Effect Controls


[BACK TO TOP](#)

In the “Effect Controls” panel, you can control parameters of elements numerically (e.g., scale, position, opacity, rotation). For example:

1. Select a video clip on your timeline.
2. Open the “Effect Controls” panel ([Window > Effect Controls](#)). This window will appear upper left.
3. Change the “Scale” of the clip from 100% to a larger or smaller percentage by typing in the new number or clicking on the left or right arrow.

Notice you can also access this panel through a tab at the top of the panel.

Other panels can change function, as well, through the tabs at the top of the panels. For example, some people like to change their Project Panel into an Effects panel (for transitions, etc.) by clicking the “Effects” Tab in the lower left panel. Then they open the Effect Controls Panel in the upper left.



Choose a Path: Beginner or Advanced

[BACK TO TOP](#)

Now is the time to choose how you want to proceed, based on your experience in Premiere Pro.

■ ADVANCED: You've Already Used Premiere Pro and Are Ready to Take Off

View the 12-minute video below as a refresher and then take off on your own in Premiere Pro. [Tube](#)

[Tube](#) Quick Overview: [Premiere Pro – Tutorial for Beginners in 12 Minutes \[2022 Version\]](#) (Skills Factory)

[Tube](#) [Premiere Pro in 11 Minutes! \[2023\]](#)

The rest of this written tutorial is optional. Use the jump menu at the top as needed.

■ BEGINNER: You'd Like Step-by-step Instruction

Continue following this written tutorial, and refer to the video below if it's helpful.

[Tube](#) In-Depth Video: [Premiere Pro for Beginners 2023: Everything You Need to Know! \[Updated\]](#) (Vince Opra)


Get Around

[BACK TO TOP](#)

■ PLAY YOUR VIDEO ON THE TIMELINE


Click the “Play” button in the Program Panel where your video appears (upper right).

This is where you will play your video to see how it looks as you create it.




■ HOW TO ZOOM & MOVE


Zoom In/Out of Video Preview



Move Your Playhead on the Timeline. Click on the top of the playhead (the blue vertical line). Drag it through the timeline, or click a new spot on the top of the timeline to make it jump there.




Zoom in/out of Timeline. Use the slider at the bottom of the timeline or use Opt/Alt and your track pad. Click and drag the right circle to make the timeline larger or smaller. Click and drag the whole slider to move through your timeline.




Enlarge Timeline View. Select the **bottom line** of a track and **drag it down or up**.

You will see images on your timeline get larger or smaller.



■ TIMELINE TRACK CONTROLS

FYI: Take a look at your timeline track controls:



■ ADVANCED ZOOM & ZOOM ANIMATIONS

YOUTUBE: ["How to Zoom in on Premiere Pro \(Tutorial\)"](#) by FilterGrade


Color Corrections

[BACK TO TOP](#)

■ CORRECT COLOR/LIGHTING


It's a good idea to make color corrections on a clip **before you cut** it and start editing.

1. If you have a top menu option for **“Color”** select it, and you will see the **color effects controls open in a panel on the right**. Change the settings as needed.
2. However, if you have the updated version, see the second screenshot.



For the new version, it's a little more complex:

1. Select the **Workspace button** (upper right)
2. Select **“Effects.”** You will see an Effects panel open on the right.
3. Go to **Window > Lumetri Color** to see the settings like the ones in pic above.



■ ADVANCED: COLOR GRADING (Optional)

Color grading is shifting the colors of all segments in a video to set a mood or adopt consistency.

Color Grading basics (without LUT's):

<https://www.youtube.com/watch?v=8lTUgg9uHRg>

<https://www.youtube.com/watch?v=Or10yLjmDp8>

Color Grading with LUTs:


<https://youtu.be/8FzX0Sz6-7Q>

Edit Clips

[BACK TO TOP](#)


■ CUT / MOVE / DELETE CLIPS

1. Use the **razor tool** (or “C” on keyboard) to cut a clip into pieces on the timeline.
2. Use the selection tool to move clips on the timeline.
3. Use the “Delete” key to delete a selected clip.




■ COPY / PASTE CLIPS

1. To **copy/paste**, select your clip and right-click for options or use Ctrl/Command-C and V.




■ DELETE SPACE

To delete the empty space, click on the space and click the “Delete” key.




■ RIPPLE DELETE (delete video clip and the gap left behind)

Ripple deleting will delete the element and also the gap it leaves behind on the timeline.



■ SHORTEN A CLIP


1. Select the clip you want to shorten.
2. Position your cursor over the end you want to shorten. Then, click and drag.



■ OPTIONAL: PRE-EDIT A CLIP IN THE SOURCE PANEL

If you want to create shorter clips before placing them on the timeline:

1. In the Project Panel, select the “Media Browser” tab to see your bins/folders.
2. In the Source Panel (upper left) click the “Source” tab
3. To trim your clip, move the **playhead to your inpoint** and click “I” on the keyboard. Then move **playhead to out point and click “O.”**
4. Then drag the clip from that panel to the timeline.




Add Audio

[BACK TO TOP](#)

ADD AUDIO TO TIMELINE


Drag your audio clip from the media bin (Project Panel) to the timeline, on an audio track.




ADJUST THE VOLUME AS NEEDED

The easiest way to do this is to:

1. Expand the size of the audio clip (see [How to Increase Timeline View](#) on a previous page)
2. You will see a white horizontal line across your audio clip.
3. Drag it down to decrease volume or up to increase volume.



FADE MUSIC IN AND OUT



This video demonstrates:

<https://www.youtube.com/watch?v=QaAgRHz5YbQ>

- Go to Window > Effects
- Click on “Audio Transitions” and “Crossfade”
- Choose “Constant Power” if you want the smoothest fades
- Drag the effect onto the end of your audio track.
- Drag out the effect icon to make the fade as long or short as you like.
- To fade in, drag the effect to the start of the music and use the same methods to alter.

ADDITIONAL SOUND ADJUSTMENTS


View this video: https://www.youtube.com/watch?v=TjfRDHod_uA (Vince Opra)

UNLINK VIDEO & AUDIO (to delete one or the other on a clip)

By default, the audio of a video clip moves with the clip.


If you want to be able to edit audio and video separately, **right-click on the clip and select “unlink.”**

Now you can manipulate audio and video separately, or delete one or the other.



■ CHANGE AUDIO SOURCES (external, internal, etc.)

Edit > Preferences > Audio Hardware



Transitions & Effects

[BACK TO TOP](#)


■ SLOW MOTION / FAST MOTION:

1. Right-click on the video clip and choose Speed/Duration.

2. You will see speed 100%.


To slow down clip, decrease the percentage. To increase speed, increase the percentage

3. To keep audio/voices at normal pitch, click "Maintain Audio Pitch" (Optional).




TRANSITIONS

1. Open your Effects Panel (Windows > Effects).
2. Select **Video Transitions**.



3. You will see the transition choices open (see screenshot below).
4. Choose **“Cross Dissolve”** (a popular option) and drag it onto a single clip OR between two clips.
5. You will see the **brown effects bar** appear on the clip(s) in the timeline.
6. Play your video to see the transition effect.
7. To **adjust the length** of the dissolve, drag the brown bar on your clip in the timeline.



Text Effects

[BACK TO TOP](#)


■ TEXT TOOL

1. Choose the **text tool**
2. **Drag a textbox** on your video
3. **Type** the words you want.
4. Use **selection tool to move**, scale, and rotate text.




■ TEXT EFFECTS:

1. With your **"Effects" Panel** still open on the right (Window > Effects), **select some text** on the video.
2. You should see the **"Essential Graphics"** effects controls open in the Effects Panel.
If not, go to **Window > Essential Graphics**.
3. Adjust font, style, color, background, alignment, kerning, leading, tracking, etc.



■ TEXT ANIMATION TEMPLATES

1. In the Essential Graphics Panel, click the **Browse tab** at the top.
2. **Choose** an animation or text effect and **drag it to the timeline**. The words will appear in pink clips.
3. To change the words in the animation, click the type on the video preview screen and edit.



CREATE GREAT CAPTIONS

Make your video fully accessible with excellent captions (YouTube captions are glitchy).

See this video: [How to Easily Create Subtitles in Adobe Premiere Pro](#)

Create Animation

[BACK TO TOP](#)

TEXT ANIMATION TEMPLATES

(See Previous Section on [Text Effects](#))

ANIMATING ZOOMS (in and out)

YOUTUBE: ["How to Zoom in on Premiere Pro \(Tutorial\)"](#) by FilterGrade

Live Writing (e.g., handwriting) and "Growth" Effect

YOUTUBE: [New Plugin](#) by Premiere Gal

KEYFRAME ANIMATION

YOUTUBE: ["How to Use Keyframes for Beginners"](#) (Vince Opra)

EASY ANIMATED SUBTITLES & TEXT

YOUTUBE: ["How to Create Animated Subtitles in Premiere Pro"](#) (Vince Opra)

Replace Background

[BACK TO TOP](#)

No Green Screen:

[How to Remove Video Backgrounds with Adobe Premiere](#)

HELPFUL TIP: Stand against a different colored wall than any color that's in your subject.

With Green Screen:


[How to Use a Green Screen with Adobe Premiere](#)

Export Video

[BACK TO TOP](#)

■ HOW TO EXPORT YOUR VIDEO

1. Go to **File > Export > Media**
2. **Name** the MP4 you're exporting.
3. Identify the **location** where you want the file saved
4. Keep defaults for the rest of settings
(NOTE: H264 is the codec for mp4)
5. Click **“Export.”** It can take time to render. This is normal.



Troubleshooting

[BACK TO TOP](#)

■ MY COMPUTER FROZE UP / STOPPED WORKING RIGHT

Restart your computer. It's normal for your computer to slow down gradually and stop working when you use big programs like Premiere Pro. It means your RAM is running low (Random Access Memory). RAM refreshes when you restart your computer.

■ MY EXPORTED VIDEO HAS IMAGES BUT NO SOUND

These are known issues with recent versions of Premiere when used with iPhone footage. Most of the time, you should have no problem, but if you do, try this before you export:

1. Go to: File > Project Settings > General > Renderer
2. You will see the setting "GPU Exceleration." Change it to "Engine Software Only."
3. Try again to export and see if it works.

■ MY EXPORTED VIDEO IS OVEREXPOSED

1. Go to Sequence > Sequence Settings.
2. Click the box called "Auto Tone Map Media."

Retouching

[BACK TO TOP](#)

■ EFFECTS CONTROL

1. Soften Pixels

Video Effects > Immersive Video > VR D-Noise

Effects Control: **D-Noise .05 or .08**

2. Glow

Video Effects > Immersive Video > Glow

Effects Control: **Glow Brightness .20**

■ LUMETRI COLOR

Warmer: Temperature 3